


How to Use Guarding Vision Share Function

Guarding Vision Share function shares device domain name.

In Guarding Vision, one device could only be added into one account; in order to solve the ‘multi people access one device’ problem, **Share** function is released.(Since V2.1)



Note:

1. Users can use GuardingVision Share function via GuardingVision APP and www.guardingvision.com web portal in order to share device to others, or manage the device shared by other;
2. Cross-regional share operation is not allowed;
3. Currently only device domain name could be shared, which means the alarm push function and the live view function in GuardingVision tab can't be shared;
4. You can set different privileges for different users by providing them with admin/guest/operator

account. The privileges are the same between different GuardingVision accounts.

Discretion

User interface may not be identical to the instructions shown below depending on the product, firmware version. However, the information and settings required to setup Guarding Vision Share function are similar across all supporting products.

Preparation




1. Users need to upgrade device to proper firmware that supports Guarding Vision Share function.
2. Users need to upgrade GuardingVision app to v2.0.2 that supports Guarding Vision Share function.

How to use GuardingVision Share function

Method 1: Use Share function via GuardingVision APP




Steps:

- (1) Run GuardingVision app at your mobile and login your account;
- (2) Go to GuardingVision tab->click your device->click Device Information -> Share Device/ View My Shared Devices;



(3) Click '**Share Device**'-> input the Guarding Vision account you want to share (email address, phone number, Guarding Vision account are supported).

Shared/Network busy/The account doesn't exist will be returned according to the results.




Method 2: Use Share function via www.Guarding Vision.com web portal

Steps:

(1) Type www.Guarding Vision.com into browser location bar;




(2) Login with your account user name and password.

A screenshot of the Guarding Vision login page. The page is titled "Welcome!". It features two input fields: "account/email" and "password". Below the input fields is a blue link that says "Forgot the Password?". A prominent red button labeled "Login" is centered below the link. A horizontal dashed line separates the login section from the registration section. Below the line, the text "No account? Register one now." is displayed, followed by a red button labeled "Register". The entire login and registration area is enclosed in a red rectangular box.

(3) Go to **Device Management** and click **Share** button . Input the Guarding Vision account you want to share (email address, phone number, Guarding Vision account are supported).

Shared/Network busy/The account doesn't exist will be returned according to the results.




How to manage my shared device


1: How to manage my shared device via app

Steps:


- (1) Run Guarding Vision app at your mobile and login your account;
- (2) Click **Manage Sharing Settings**, all the accounts that this device has been shared to would be displayed.



(2) Click  to select the account you want to stop sharing. You can also disable all the sharing.




(3) If you disable all the sharing, it would look like this:



2: How to manage my shared device via web portal

Steps:

(1) Click  to check all the accounts that this device has been shared to. The  could only be seen when there is a share under your device.




The screenshot shows the 'Device Management' web portal. On the left sidebar, there are three menu items: 'Device Management' (selected), 'Devices Shared by Others', and 'My Account'. The main content area has a search bar for 'Device Serial No.' and an 'Add' button. Below is a table with the following data:

Device Domain	Device Serial No.	IP/Port No.	Status	Device Operation
523307819	523307819	<input type="text"/>	Offline	   
623050060	623050060	<input type="text"/>	Offline	   
650722192	650722192	<input type="text"/>	Online	   

Below the table, there is a section titled '650722192 is shared to the accounts:' with a 'Delete All' button. It contains two rows, each with an input field and a delete icon.

(2) Click  to select the accounts you want to stop sharing. You can select one account or all accounts.




How to manage the device shared by others

1: How to manage the device shared by others via app

Steps:


- (1) Run Guarding Vision app at your mobile and login your account;
- (2) Go to Device tab-> click **Manual Adding**-> select Register Mode as **Guarding Vision Domain**->go to **Device Domain**, then you can find the device shared by others. Together with the shared device are the device domain name & the account which shares this device.



2: How to manage the device shared by others via web portal

Steps:


(1) If your account receive a share, there will be an **Device Shared by Others** column on web browser.



The screenshot shows a web portal interface with a sidebar on the left containing three menu items: 'Device Management' (gear icon), 'Devices Shared by Others' (gear icon with a red border), and 'My Account' (person icon). The main content area is titled 'Devices Shared by Others' and contains a table with the following data:

Device Domain	Shared Account	IP/Port No.	Status	Device Operation
529565480	<input type="text"/>	<input type="text"/>	Online	 

(2) Click **Edit**  to edit the device domain.



The screenshot shows the 'Edit Device Information' dialog box overlaid on the 'Devices Shared by Others' page. The dialog box has a title bar 'Edit Device Information' and contains a label 'Device Domain:' followed by a text input field with a question mark icon to its right. At the bottom of the dialog box are two buttons: 'Cancel' and 'Ok'.

(3) Click  to delete the device that others shared to your account.

Device Management

Devices Shared by Others

My Account

Devices Shared by Others

Device ID	Status	Device Operation
52956548	6413 Online	 

Delete

Delete the device from this account?

Cancel